Download & Install Read & Write Gold for Mac

Go to the Read&Write Gold section of the UIT Software Portal:

- 1. Click the Read and Write Gold (6.0.5) link next to Mac OS X.
- 2. Click the **Download button**. (RWG is a big file, it could take 10 minutes or so to download depending on your connection)



Once the file has finished downloading you will need to adjust the security settings on your computer to in order to install. Choose the instructions appropriate for your Mac's OS:

MacOS Sierra (10.12) Instructions

Mac OS 10.11 (and older versions) Instructions

Adjust security setting:

- a) Click the **Apple icon** on the top menu bar.
- b) Select System Preferences > Security & Privacy.




c) Click the **lock icon** in left corner.



- d) Enter your computer's password when prompted.
- e) Select **Anywhere** located under *Allow apps downloaded from:*
- f) Click **Allow from Anywhere** button when prompted.

Install and Activate (for all Mac OS versions):


- 1) Go to the Downloads folder on your computer (or wherever you downloaded the installer file) and click **ReadWriteGold.dmg** to open.
- 2) Click Read&Write Gold.app.
- 3) Click the **Open button** when prompted.



4) Click the Activate button (leave activation code field blank).

If you are prompted for an access code:


5) Copy and paste this number into the Access Code field and then click **Login**. **2917927F6671033**



The Read&Write Gold toolbar will open and be displayed on your screen.



6) Click the **Allow button** when asked to accept incoming network connections.



You are ready to use R&WG.

You may be asked to download an RWG extension or plug-in for your browsers, after installing R&WG. Follow the prompts to install.

To reset your computer's Security setting, OS 10 versions 11 and older users should return to the Adjust security section above and repeat steps until step e., where you can change the setting from Any back to App Store and identified developers. Click the lock icon to save setting.


MacOS Sierra users, go to the Return to original security setting section below.

See the <u>Learn how to use Read &Write Gold section</u> on the last page for how-to information and quick start guides.

MacOS Sierra (10.12.) Instructions

Adjust security setting:

- 1. Open Finder and go to Applications > Utilities.
- 2. In the **Utilities** folder, locate and open **Terminal**.



3. In **Terminal**, type (or copy then paste) the command below as shown below. sudo spctl --master-disable

```
mike — sudo — 80×24

Last login: Thu Oct 27 11:45:19 on ttys000

[bayhastmacbook9:~ mike$ sudo spctl —master—disable

Password:

Password:
```

4. Enter your computer's password.

Go to the <u>Install and Activate (for all versions) instructions</u> above to complete installation and activation.

After you have completed installation you can reset the security settings by following steps 1 and 2 above, then continue below:

Return to original security setting

3. Type (or copy/paste) the following line in the Terminal:

```
sudo spctl --master-enable
```

4. Enter your computer's password as before.

```
mike — sudo — 80×24

Last login: Thu Oct 27 11:45:19 on ttys000

[bayhastmacbook9:~ mike$ sudo spctl --master-enable

Password:

Pa
```

Quit the Terminal. Your settings will now be reset.

Learn to use Read&Write for Mac

- Quick Reference Card
- Quick Start
- Online Help
- Videos

Videos can also be accessed via the R&WG application. To access them, open R&WG, click Help in the top menu bar and select Video Tours.